

		ORG	0	別紙一
0000 F3	L0000 :	DI		
0001 31FFFF		LD	SP, LFFFF	
0004 C33B00		JP	L003B	
	;			
0007 00		NOP		
0008 C36A00		JP	L006A	
	;			
000B C35717	L000B :	JP	L1757	
	;			
000E AB		XOR	E	
000F F0		RET	P	
0010 C35942		JP	L4259	
	;			
0013 C36A00	L0013 :	JP	L006A	
	;			
0016 DA0CC3		JP	C, LC30C	
0019 A6		AND	(HL)	
001A 40		LD	B, B	
001B F3		DI		
001C 0B		DEC	BC	
001D C37E50		JP	L507E	
	;			
0020 C3DAF1		JP	LF1DA	
	;			
0023 C39C27		JP	L279C	
	;			
0026 88		ADC	A, B	
0027 0C		INC	C	
0028 C3DDF1		JP	LF1DD	
	;			
002B C3600D		JP	L0D60	
	;			
002E 46		LD	B, (HL)	
002F 0C		INC	C	
0030 C3E0F1		JP	LF1E0	
	;			
0033 9F		SBC	A, A	
0034 0F		RRCA		
0035 C35702		JP	L0257	
	;			
0038 C3E3F1		JR	LF1E3	
	;			
003B AF	L003B :	XOR	A	
003C 3275EA		LD	(LAE75), A	
003F CDF10C		CALL	L0CF1	
0042 30C7		JR	NC, L000B	
0044 18CD		JR	L0013	
0046 00		NOP		
0047 00		NOP		
0048 00		NOP		
0049 00		NOP		
004A 00		NOP		
004B 00		NOP		
004C 00		NOP		
004D 00		NOP		
004E 00		NOP		
004F 00		NOP		
0050 00		NOP		
0051 00		NOP		
0052 00		NOP		
A			B	

PC-8001 BASIC SOURCE PROGRAM LISTINGS

別
紙
二

PC-8001 BASIC SOURCE PROGRAM LISTINGS

	1	□	ORG 0	
0000	F3	:	DI	
0001	31FFFF	:	LD SP,0FFFFH	
0004	C33B00	:	JP WAMCHK	;CHECK COLD START OR WARM START
0007	00	:	DB 0	
0008	C36A00	:	JP BASHOT	;RESTART 08H TO BASIC WARM START
000B	C35717	:	RECOL: JP COLDST	;BASIC COLD START
000E	ABF0	:	DW FACC+3	
0010	C35942	:	JP CHRGEI	;RESTART 10H TO GET CHARACTER
0013	C36A00	:	REWARM: JP BASHOT	;BASIC WARM START
0016	DA0C	:	DW CCHROT	
0018	C3A640	:	JP CHROUT	;RESTART 18H TO OUTPUT CHARACTER
001B	F30B	:	DW CHNIT	
001D	C37E50	:	JP POS2	
0020	C3DAF1	:	JP HOOK38	;RESTART 20H FOR USER
0023	C39C27	:	JP CINT3	;REGISTER HL TO FLOATING ACCUMULATOR
0026	880C	:	DW CCHRIN	
0028	C3DDF1	:	JP HOOK39	;RESTART 28H FOR USER
002B	C3600D	:	JP LPTCHR	;OUTPUT CHARACTER TO PRINTER
002E	460C	:	DW COINIT	
0030	C3E0F1	:	JP HOOK40	;RESTART 30H FOR USER
0033	9F0F	:	DW KSCANO	
0035	C35702	:	JP CONOUT	;DISPLAY CHARACTER
0038	C3E3F1	:	JP HOOK41	;RESTART 38H FOR USER
	1	□		